



POI Loader Guide for Garmin GPS

load your POI step by step onto your Garmin GPS


How to load easily POI into Garmin GPS, follow step by step the guide below :
(Click image to enlarge)

Step 1 : Download POI

Save the file corresponding to the POI you want to load into your GPS.

For this, click on the file link and choose a folder to save where you can easily remember. For example create a folder "POI" on the disk C:

Note : This folder can contain more than one file, they will be loaded into your GPS



Step 2 : Download and install the Garmin software POI Loader

Garmin POI Loader is a free software for your computer that lets you load points of interest (POIs)

Click to the link below to download and install the software POI Loader

<http://www8.garmin.com/products/poiloader/>



Step 3 : Launch the POI Loader software

Once the installation is complete, if the software does not start automatically, launch it from the Start Menu item

The software is running, click on Next for start the POI loader




Step 4 : Select the destination of your POI

To load the POI into your GPS, select 'Garmin Device'

Plug your GPS to your computer with the Garmin USB cable.

Wait several seconds until your GPS is connected then click Next to go to the next step



Step 5 : Select your device

Select your GPS in the list of device.

Note : If your device is not listed, click 'Find Device' to launch a new detection

Click Next to go to the next step



Step 6 : Select the update mode

Select the first option 'Install new custom POI's onto your device' then click Next to go to the next step

Note : If you choose the second option, all your custom POI will be deleted




Step 7 : Select the configuration

Click on the browse button to select the folder of your POI.

For example, you can browse to C:\POI

Check that the units are in your convenience

Click Next to launch the POI loading into your GPS



Step 8 : Load complete

The message show the number of POI loaded into your GPS

It is the last step. Click Finish to close the POI Loader software



Step 9 : View the POI onto your GPS

The POI are loaded into your GPS.

You can turn off and unplug your GPS from your computer

To view the POI, turn on your GPS and select your categories of POI.

Note : even if you choose not to permanently display the POIs, you can reach them and find them near where you are.



© 2009 GO2PO1 Tous droits réservés. Reproduction interdite sans autorisation. [Idexis](#)